

KORG

KORG Gadget

MOBILE MUSIC STUDIO

Studio Guide

Thank you very much for purchasing the **KORG Gadget Mobile Music Studio**. To take full advantage of this product and to ensure trouble-free operation, please read this owner's manual carefully and use the product as directed.



<http://www.samplemagic.com>

The logo for Loopmasters, with the word 'loopmasters' in a lowercase, sans-serif font, where the 'o' is blue and the rest is black. The logo is set against a black rectangular background.

loopmasters

<http://www.loopmasters.com>



PRIME LOOPS
GET THE SOUND

<http://www.primeloops.com>



<http://www.rawcutz.com/>

- * Apple, iPad, iPhone, iPod touch, and iTunes are trademarks of Apple Inc., registered in the U.S. and other countries.
- * All product names and company names are the trademarks or registered trademarks of their respective owners.

Table of contents

Quick reference	5
Basic Information	5
Prepare to Play a Gadget	7
Play a Synthesizer Gadget.....	7
Edit the Tone of the Synthesizer	11
Play a Drum Gadget	12
Edit the Tone of the Drum.....	13
Main screen.....	14
1. Header	15
2. Song Section	16
3. Mixer Section	17
4. Footer.....	19
Edit screen.....	20
1. Header	21
2. Piano Roll.....	22
3. Gadget Panel.....	23
4. Footer.....	26
Create a Song.....	27
Create a Song By Combining Gadgets	27
Set the Volume, Pan, and the Depth of Effect for Each Track	31
Save Songs.....	31
Edit.....	32
Other Parameters	41
Bluetooth MIDI.....	41
MIDI Input.....	41
MIDI Sync	41


Ableton Link.....	41
WIST	42
Dropbox.....	42
Others.....	42
Export.....	43
Specificatons.....	44
Support and service	46

Quick reference

Basic Information

Components of KORG Gadget

Gadget has the following components:



Song

Gadget manages one song in the unit called "Song". It doesn't matter if you play a song with one gadget or finish up with several tracks, Gadget will save it as a Song.

Items saved in one Song:

- Scene and clip status
- Tone of each gadget
- Mixer settings
- Settings for tempo and swing etc.


Track

Track is one part of the sequencer/mixer that's used to play one gadget. Track consists of a "Gadget" and a "Scene" with several bars.

Scene

A scene includes several bars.

In general, one song consists of an "Intro", a "Verse", and a "Chorus" sections that are made up with several bars. These components are called a "Scene."



Clip

"Clip" refers to the data of each track in a scene.

This can be individually set for each track, and the different number of bars per clip can be set in the same scene.

Prepare to Play a Gadget

Tap the KORG Gadget icon displayed on the Home screen of the iPad to begin. Make sure the volume of the iPad is turned up.

Tip: Use a headphone or external speaker (amplifier built-in speaker) to enjoy higher quality sound.


Play a Synthesizer Gadget

Let's start to play a gadget by selecting the Berlin synthesizer gadget.

1. From the main screen.


In the main screen, you can assign a gadget to each track, edit scenes, and adjust the volume of each track.

Main screen



KORG Gadget – Studio guide


2. Tap Add Track button to add a track.



The gadget select screen will be displayed.

Cancel	New Track : Choose a Gadget	Overview
	London Hypersonic PCM Drum Module	Drums PCM Basic
	Marseille Polyphonic PCM Synthesizer	Poly PCM Basic
	Berlin Monophonic Synchronized Synthesizer	Lead Analog Sync
	Chicago Tube Bass Machine	Bass Hybrid Tube
	Phoenix Polyphonic Analogue Synthesizer	Poly Analog Basic

3. Select the Berlin synthesizer gadget from the gadget select screen.
4. Tap the Clip.



The edit screen will be displayed. The edit screen consists of the Piano Roll and gadget panel. The edit screen allows you to do the following:

- Play a gadget and edit the tone.
- Record to a track and edit the data.

Edit screen



5. Play the gadget using the keyboard displayed on the bottom of the screen. The gadget will produce sound when you tap or slide the keyboard.



If you come up with a cool phrase or pattern while playing, you can record it by referring to “Create a Song” on page 27.

Edit the Tone of the Synthesizer

Let’s edit the tone of the synthesizer.

1. Use the knobs, sliders and buttons to edit the tone. If you have multiple edit pages, you can switch between the pages by tapping the button or switch.

Edit page selector switch



Tip: Use the knob by using the iOS settings.

Play a Drum Gadget

Now, let's play a drum gadget.

1. Tap the Add track button on the main menu.
The gadget select screen will be displayed.
2. Select a drum gadget from the select screen.
Here, we will select "London."
3. Play the gadget by tapping the pad displayed on the screen.



Edit the Tone of the Drum

Let's edit the tone of the drum.

1. Use the on-screen knobs, sliders and buttons to edit the tone.
You will see a page selector button if there are multiple edit pages. Tap the button to switch between the edit pages.




Tip: Use the knob by using the iOS settings.

Main screen

This screen allows you to check the entire view of tracks and scenes. You can do the following:

- Assign a gadget to each track.
- Add, copy and delete scenes, change the beat, etc.
- Adjust the volume and insert effects into each track.



1. Header



a. File button

Tap this button to display the menu, where you can load and save song data etc.

New: This command creates a new song.

Open: This command opens a saved song.

Save: This command overwrites and saves the currently open song.

Save As: This command saves the currently open song with a different name.

Export: This command exports the currently open song as an audio file. (See “Export” on page 42.)

b. Gadget Cloud button

Tap this button to connect to the music sharing service “GadgetCloud.”

c. Information

Shows information such as the software version of the app.

d. Song name

This displays the name of the song. Tap this to change the name.

e. Expand button

This button hides the mixer section and expands the song section screen.

f. Settings button

This button sets Bluetooth MIDI, MIDI Sync, WIST, etc. (See “Other Parameters” on page 41)

g. Help button

This button displays the help screen including operating procedure.

Manual: This displays the operation manual.


Help Center: This displays the KORG app Help Center.

Bug information: This displays bug information from the KORG app Help Center.

Note: In order to display the operation manual, KORG app Help Center or bug information, the device must be connected to the Internet.

2. Song Section

The song section displays tracks, scenes, and clips. Tap the clip to move to the edit screen and display the content and gadget for the clip.



a. Add Scene button

This button adds a scene.

b. Scene number


This button displays the scene number. If you tap ▶, only that scene will be played.

c. Clip

This button displays the notes recorded in each scene. Tap this button to display the edit screen.

3. Mixer Section

The mixer section sets the volume level and pan of the master, and also the volume level, pan, solo/mute status of each track.



a. Gadget

This button displays the gadget that's assigned to the track. Tapping this button will display the edit screen.

b. Add Track button

This button adds a track. Tapping this button adds a track, and then the gadget select screen will be displayed.

Select the gadget you want to assign to the track from the screen.

c. Master Effect

Limiter Switch

This switches the Limiter on/off.

Limiter Depth knob

This knob sets the Limiter depth.

Reverb Switch

This switches the Reverb effect on/off.

Reverb Time knob

This knob sets the reverb time.

d. Pan knob, Send knob

Pan knob

This knob sets the sound location of each track or master.

Send knob

This knob sets the send level to Master Reverb effect for each track.

e. Fader

Fader sets the volume level of each track or master. Master sets the volume of the entire sound. The level meter will be displayed on the right.

f. Solo button

This button outputs only the sound of the corresponding track.

g. Mute button

This button mutes the sound of each track.

h. MIDI button

When this button is lit in yellow, the corresponding gadget can be controlled by an external MIDI controller connected to the iPad/iPhone. The MIDI settings can be switched to the Advanced mode. With this mode, the MIDI input device and the MIDI channel can be set for each track (See “Other Parameters” on page 41).

i. IFX button

This can select five insert effects for each track.

4. Footer



a. Function button

This button displays the functions menu. In the functions menu, tap the displayed button.

b. (REC) button

This button records the performance in real time.

c. (STOP) button

This button stops recording or play back.

d. (PLAY) button

This button plays the performance. Press this button while playing the performance to pause.

e. (Loop) button

This button loops the scene.

f. Tempo button

Tap this button to display the dialog box. You can set the tempo, etc.

Tempo

This sets the tempo of the performance.

Swing


This sets the amount of swing.

Tap

Tap this to set the tempo.

Metronome


This switches the metronome on or off.




Edit screen

The edit screen consists of the Piano Roll and the gadget panel. You can do the following:

- Play a gadget and edit the tone.
- Record a song and edit the recorded data.



1. Header



a. Back button

This button returns to the main menu.

b. Selector buttons

These move to the previous or next track.

c. Scene and gadget


These display the names of the scene and gadget that are currently being edited. Tap this to display the gadget select screen.

d. Expand button

This button expands the Piano Roll.

2. Piano Roll

Piano Roll displays the notes that are recorded in the clip of each track. Record the notes to the clip by recording in real-time or by manually inputting the notes by touching the screen. It is also possible to edit the notes after recording in real-time.



The Piano Roll displays the notes on the longitudinal axis. The note display can be switched by Note Fold of [* Bar] in the function. Tap the note to make a sound.

a. Locator

This displays the location of clip on the horizontal axis. If there are multiple bars in the clip, tap the bar display, “2 Bar” or “3 Bar”, etc. to display contents of that bar.

b. Note display

This displays the notes that are recorded in the clip. The shade of color changes depending on the velocity value.

c. Parameter display

This displays the parameters that were captured during the recording. Tapping the parameter expands the display towards the top, which allows you to edit the parameter value, etc.

d. Draw/Select button

This button is used to edit a note.


Please refer to “Add and Record Scenes” on page 29 for editing notes.

e. Erase button

If you keep touching this button while playing, the recorded notes will be deleted.

3. Gadget Panel

The Gadget panel includes the tone parameters as well as the keyboard or pad.



a. Edit screen selector button/switch

This button/switch is displayed when you have multiple edit screens. Tap this button to switch between the edit screens.

b. Program display

This displays the tone name. Tap this to display the tone list. Select a tone from the list.

c. Program Select button

This button selects the program. The program is switched one at a time every time you tap the button.

d. Parameter

This displays the parameter of a gadget. Use a knob or switch to edit the tone. If you use these knob or switch during recording, the operation will be recorded.

Tip: Use the knob by using the iOS settings.

e. Scale button

Tap this button to display the dialog box. Set the scale of the performance using the keyboard.

Scale Type

Sets the scale that will be produced using a keyboard.

Key

This sets the key that serves as a reference for the scale.

Scale Step

This sets the notes that will be produced in one octave.

f. Octave button

This button sets the octave that will be produced using a keyboard.

g. Keyboard, pad

In the synthesizer gadget, you can play a scale by tapping or sliding the keyboard. Tap the Scale button to set the scale. Tap the pad for the drum machine gadget.

Assign MIDI Control Change Messages to Knobs and Switches

MIDI control change numbers (MIDI CC#) can be assigned to the knobs, sliders and switches of each gadget. The gadgets can then be controlled by the external MIDI controller connected to the iPad.

1. Connect the external MIDI controller to the iPad.

For details on making connections, refer to the manual for the external MIDI controller.

2. Tap the Function button on the edit screen to display the functions menu.
A dialog box for assigning the MIDI CC# is displayed in the lower right of the screen.



3. Tap the parameter to be assigned the MIDI CC#. The selected parameter will blink in grey.



4. Operate the external MIDI controller connected to the iPad. The gadget receives the MIDI CC# sent from the controller, and the MIDI CC# is assigned to the selected parameter.

Tip: To use the external MIDI controller to control a gadget parameter assigned a MIDI CC#, tap the MIDI button for a gadget in the mixer section of the edit screen so that the button lights in yellow.

4. Footer



a. Function button

This button displays the functions menu. In the functions menu, tap the displayed button.

b. (REC) button

This button records the performance in real time.

c. (STOP) button

This button stops recording or play back.

d. (PLAY) button

This button plays the performance. Press this button while playing the performance to pause.

e. (Loop) button

This button loops the scene.

f. Tempo button

Tap this button to display the dialog box. You can set the tempo, etc.

g. Quantize button

This button sets the resolution of the recording. This also corrects the timing of notes that are played during real-time recording.

h. Solo button

This button will only output the sound of track that is currently selected.

i. Mute button

This button mutes the sound of track that is currently selected.

j. Undo button

This button undoes the editing operation for the currently selected track.

k. Redo button

This button redoes the editing operation for the currently selected track.


Create a Song

Create a Song By Combining Gadgets

To create a song with the KORGE Gadget, find your favorite gadget first.


Let's start by selecting one gadget to play. Once you come up with a pattern, record it to the scene. Add other gadgets to the sections where you feel they're needed. By repeating this process, your original composition will grow and flourish.

Select a Gadget to Play


1. Tap the  (File button) on the main screen and select "New" from the menu displayed.
2. Name the gadget if necessary, and tap "OK".
The gadget select screen will be displayed.
3. Select the gadget from the select screen.
The screen will be changed to the edit screen.
4. Edit the tone of the gadget or play it.
Once you come up with a pattern or phrase, record it to the clip.

Record

1. Tap the Function button on the main screen to display the functions menu.



- Set the beat of scene and the number of repeats in the dialog box that is displayed by tapping [4/4 x 1].




Signature: Sets the beat.

Repeat: Sets the number of times to repeat the scene during playback.

After adjusting the settings, tap outside the dialog box to close it.

- Set the number of bars in the dialog box that is displayed by tapping [1 Bar].



Bars: Sets the number of bars in the clip.

Play Mode: Sets the method to play the clip.

Mute: Mutes tracks.

Note Fold: Switches the note display of the Piano Roll.

Grid: Sets the resolution of the quantize function. The grid display on the screen changes with the settings.

After adjusting the settings, tap outside the dialog to close it.



- Tap the Function button to stop editing the function.
- Tap the created scene button to display the edit screen.

6. Tap the  (REC) button to enable record stand-by status. Tap each button on the footer to arm them for recording.

Quantize button: This button quantizes notes with the resolution that is set by the Grid [* Bar] parameter in the functions menu.

 **(Loop) button:** This button loops the scene of the selected clip.


Tempo button: This button sets the tempo.

7. Tap the  button to start recording. Play a gadget.
If you use a knob or switch of a gadget during the recording process, the operation will be recorded and the tone will be changed during playback.
8. After the session, tap the  button to stop recording.

Tip: If content has been recorded, the Undo button appears in the footer. With this button, an operation can be undone or redone.

Add and Record Scenes

1. Tap the Add Scene button on the main screen to add a scene.
You can also delete a scene or add a duplicate in function that is displayed by tapping the Function button.



Delete: Deletes a scene.

Insert: Inserts a blank scene of the selected scene in the back.

Duplicate: Inserts a copy of the current scene in the back.

2. Set the scene.
See Step 2 to 4 of “Record” on page 27
3. Record in the scene.
See “Record” on page 27


Add Tracks

1. Tap the Add Track button on the main screen.
2. Set the number of bars in the dialog that is displayed by tapping [* Bar] in the functions menu.
See Step 3 of “Record” on page 27
3. Play a gadget on the edit screen and record the pattern and phrase.
See “Record” on page 27

Repeat the above procedure to create a song.

Delete Tracks and Add Duplicates

1. Tap the Function button on the main screen to display the function.




2. Tap [Delete] displayed in the mixer to delete a track. Tapping [Duplicate] will add a duplicate of the track on right-hand side.
3. Tap [Change] to change the gadget.
The gadget select screen will be displayed.
4. Tap [Freeze] if the number of tracks, scenes or bars is increased and operation becomes sluggish.
The freeze function is turned on and the load on the CPU is reduced.

Set the Volume, Pan, and the Depth of Effect for Each Track

After the recording is completed, set the volume and pan of each track while playing the song.

Save Songs

Saves the completed song.

1. Tap the  (File button) on the upper left side of the main screen to display the file menu.
2. Select “Save As” from the menu.
3. Input the name in the displayed dialog.
4. Tap “OK” in the dialog.


Edit

Copy a Bar of Note Data


With the “COPY” command in the functions menu, a bar of note data can be copied.

Note: The “COPY” command cannot be used if there are less than two bars of notes. Before copying, be sure to create multiple bars.


1. Tap the Function button on the edit screen to display the functions menu.
2. Tap the COPY button in the upper right of the screen.




The screen for selecting the bar to be copied will be displayed




3. Tap the bar to be copied.



The screen for selecting the destination of the copied bar will be displayed.




4. Tap the bar where the copied bar will be added.



Copying is finished.


Note: Multiple bars cannot be copied.

Edit Notes

1. Tap “Draw” on the Draw/Select button to enable the Draw  status. With this status, you can move, add, or delete notes by tapping or dragging on the screen with a finger.


Move Notes

Drag the center of note to move it.




Change the Length of Note

Change the length of note by dragging the back side of note.




Add Notes

Add a note by tapping the area with no note.





Delete Notes

Tap the note to delete.



Select Multiple Notes to Edit


1. Tap “Select” on the Draw/Select button to enable the Select  status. With this status, you can select the notes on the screen with a finger to edit.
2. Select or draw a box around the note you want to edit with a finger. The color of the note you selected changes to white.




3. You can edit the note, and perform tasks such as: deleting the selected note and raising or lowering one pitch at a time.

Delete All Notes in a Track

1. Tap the Function button to display the functions menu.




2. Tap the Clear Note button from the buttons that appeared in the upper left of the screen. All notes in the track being edited are deleted.





Edit Parameters


1. Tap the parameter preview on the bottom of the note display to show the parameter.




The parameter of the recorded note will be displayed with graphics. The name of the editable parameters will be displayed on the left side. The parameter that is recorded in the clip will be displayed in white on the right end of the parameter name.



2. Tap “Draw” to enable the Draw  status.
3. You can change the value by dragging the top of the graphics on the screen up and down.
You can change the Edit button to “Select” to edit the parameter.
4. If you want to edit other parameters, tap the parameter name displayed on the left.




To return the screen back to the note, tap the note that is displayed on the parameter display.




Delete All Parameters for a Track

1. Tap the Function button to display the functions menu.



2. Tap the Clear Automation button from the buttons that appeared in the upper left of the screen.
All parameters recorded with the track being edited are deleted.



Other Parameters

Bluetooth MIDI

From this menu, you can select the Bluetooth MIDI device (microKEY Air, nanoKONTROL Studio, nanoKEY Studio, etc.) to connect to. Select your Bluetooth MIDI device in order to use it. (For compatibility with the KORG Gadget, check with the manufacturer of your Bluetooth MIDI device.)

MIDI Input

Select the MIDI input setting mode.

Easy: These are the basic conventional settings. MIDI input is enabled for the track whose MIDI button is lit in yellow in the edit screen. (Multiple MIDI buttons cannot be selected.)

Advanced: The MIDI device and MIDI channel settings can be specified for each track. Tap the All button in the edit screen to specify advanced settings. (This mode is for advanced users.)

MIDI Sync

The setting for MIDI clock synchronization between the iPad running KORG Gadget and the connected external MIDI device can be specified. Tap “Int”, “Ext” or “Auto” from “MIDI Sync” to select the setting.

Int: KORG Gadget operates using its internal clock. Select this setting when KORG Gadget is used by itself or when an external MIDI device is synchronized to the iPad as the Master (controlling side).

Ext: KORG Gadget operates synchronized to the MIDI clock of the connected external MIDI device.

Auto: Normally, the operation is the same as with “Int”. If KORG Gadget receives a MIDI clock from the connected external MIDI device, the operation automatically switches to “Ext”.

Ableton Link

Ableton Link is technology for synchronizing beats, phrases and tempos of Ableton Live and a Link-enabled iOS app via a wireless network.

This gives you the freedom to play from multiple devices, like in a live band. While someone is playing, other members can participate in the performance so that everyone can follow along on their devices and even change the tempo.

Using apps with Ableton Link built in, you can play together in time from multiple devices or from multiple apps used simultaneously on the same device.

Ableton Link: This switches the function on/off.

In-app notification: This displays a message when an app compatible with Ableton Link is connected.

Connected Apps: This displays the number of currently connected apps.

WIST

WIST is a function that allows a performance to be started wirelessly in apps on two iPads near each other at the same time. Enhance your enjoyment by performing together with a friend or by yourself using two iPads.

The app that controls playing/stopping is the Master, and the other, which is controlled, is the Slave. When the performance is started, the Slave is automatically set to the tempo information of the Master.

WIST ON: This starts detection of the nearby iPad/iPhone. Depending on the communication conditions, detection may take some time.

WIST OFF: This disables the WIST connection.

Dropbox

The setting for linking with Dropbox can be specified. When exporting to Dropbox, the data is uploaded to the linked Dropbox account.

Unlinked: Tap this button to display the Dropbox login screen.


Login Name: Tap this button to log off of Dropbox.

Others

This displays the iOS settings screen for Gadget. This allows you to specify settings for audio latency, background audio, etc.

Export

The song is exported as an audio file in the WAV format (16-bit, 44.1 kHz stereo).

1. Tap  (File button) in the upper left of the main screen, and then select “Export” from the displayed menu.
2. From the Export menu, select the location where the audio file will be saved.

GadgetCloud

This uploads the exported audio file to the “GadgetCloud”, which allows you to publish songs to KORGE Gadget users worldwide.

Note: GadgetCloud is based on the music sharing service “SoundCloud”. You must have already registered an account with SoundCloud before using this function.

iTunes

This saves the exported audio file to an iPad. The saved file can be transferred to a computer through iTunes.

Dropbox

This uploads the exported audio file to Dropbox.

Note: You must have already registered an account with Dropbox.

Audio copy

This moves the exported audio file to the Clipboard. The audio data can be used with AudioPaste-compatible applications.

Ableton Live Project

This saves the exported audio file to an iPad or uploads it to Dropbox as an Ableton Live project file for each track. Specify iTunes or Dropbox in the menu.

Standard MIDI File

This exports the current song as a Standard MIDI File. Specify iTunes or Dropbox in the menu.

3. When exporting audio data, you can select one of the following settings.

Master: The data for all tracks will be exported in the audio data.

Track: Only data for the specified track will be exported in the audio data.

Specifications

Operating requirements

OS

iOS 8 or later, native 64 bit support

Device

iPad Pro, iPad Air2, iPad Air, iPad (4th generation), iPad (3rd generation), iPad 2
iPad mini 4, iPad mini 3, iPad mini 2, iPad mini
iPhone6s Plus, iPhone6s, iPhone6 Plus, iPhone6, iPhoneSE, iPhone5s

* For the ideal experience, we recommend that you use the most recent iOS device. Due to differences in the screen size and CPU speed, we recommend using iPhone 6 or later. iPhone 5/5c/4S are not supported.

- For the ideal experience, we recommend that you use this with the most recent iPad.
- The Freeze function allows you to conserve CPU power and use a larger number of gadgets simultaneously.

Specifications

Number of Instruments

Total of 26 Gadgets

- Included in download: 15 Gadgets
- Available with in-app purchase: 5 Gadgets
- With purchase of KORG Module: 5 Gadgets (available with Module purchase)
- With purchase of KORG iM1: 1 Gadget (available with iM1 purchase)

Number of Programs

More than 300

Number of Samples

More than 500

Number of Songs

Unlimited (depends on the specifications of your iPad/iPhone)

Number of Instrument tracks

Unlimited (depends on the specifications of your iPad/iPhone)

Resolution

♩/480

BPM

20.0 – 300.0

Swing

0 – 100 %

Master Effects

Reverb, Limiter

Insert Effects

Total of 10 effects (5 can be inserted into each track.)

MIDI

Supports playing from an external MIDI device

Audio Export

- Share and View Tracks on GadgetCloud powered by SoundCloud
- MIDI File Export
- Ableton Live Project Export Compatible
- Upload to iCloud or Dropbox
- Export to iTunes
- Bundled with Ableton Live Lite
- AudioCopy Compatible

Other Features

- Inter-App Audio Compatible
- Audiobus Compatible
- WIST Compatible (Wireless Sync-Start Technology)
- Ableton Link Compatible

* Appearance and specifications of products are subject to change without notice.

Support and service

If you have questions about this product, please contact the Korg distributor in the country where you purchased it.

Information to provide when contacting us

In order for us to help you, we'll need the following information since product support cannot be provided without it

- Your name
- The name and version of the product (How to check the version)
- The name of the device that you're using
- The version of the operating system
- Your question (provide as much detail as possible)

Before you contact us

- Before you contact us, check whether this manual or KORG app Help Center has an answer for your question.
- Please be aware that we cannot answer questions about products that are not made by Korg, such as basic operation of your hardware device, or general questions about creating songs or sounds.

KORG INC.

4015-2 Yanokuchi, Inagi-City, Tokyo 206-0812 JAPAN

© 2014 KORG INC.